NOVELL® RESEARCH

Overview of NetWare 4.0 New Features

Robert E. Jones
Senior Technical Writer
Systems Research Department

NetWare 4.0 offers many new and exciting features not found in previous versions of NetWare. This AppNote highlights the most important new features and gives a feature-by-feature comparison between NetWare 4.0 and NetWare 3.11.

Copyright (c) 1993 by Novell, Inc., Provo, Utah. All rights reserved.

No part of this document may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without express written permission from Novell, Inc.

Disclaimer

Novell, Inc. makes no representations or warranties with respect to the contents or use of these Application Notes (AppNotes) or of any of the third-party products discussed in the AppNotes. Novell reserves the right to revise these AppNotes and to make changes in their content at any time, without obligation to notify any person or entity of such revisions or changes. These AppNotes do not constitute an endorsement of the third-party product or products that were tested. Configuration(s) tested or described may or may not be the only available solution. Any test is not a determination of product quality or correctness, nor does it ensure compliance with any federal, state, or local requirements. Novell does not warranty products except as stated in applicable Novell product warranties or license agreements.

Contents

| Introduction | | | | | | |
|--------------------------------|------|------|------|--|--|--|
| NetWare 4.0 New Features | | | | | | |
| NetWare Directory Services | | | | | | |
| Server Memory Management | | | | | | |
| Data Storage Management | | | | | | |
| Block Suballocation | | | | | | |
| File Compression | | | | | | |
| Data Migration | | | | | | |
| High Capacity Storage System | | | | | | |
| Auditing | | | | | | |
| Other New Features | | | | | | |
| Running NLMs in Protected Mode | | | | | | |
| Packet Burst Protocol | | | | | | |
| Large Internet Packets | | | | | | |
| Multiple Languages | | | | | | |
| NetWare Print Services | | | | | | |

| NetWare 4.0 Utilities | | | | | | | | | | | | | | | | |
|----------------------------|------|------|--|--|--|--|--|--|------|--|--|------|--|------|--|--|
| NetWare Feature Comparisor | | | | | | | | | | | | | | | | |

Introduction

NetWare 4.0 is the most advanced and powerful network operating system available today. This release represents the ninth generation of NetWare development. It adds a whole new dimension to network computing, extending network services and making network management easier than ever.

Currently, peer-to-peer networking is receiving a lot of attention in the computer industry. Although these types of networks can address the needs of small businesses or departments, they tend to introduce resource security and management problems in a corporate networking environment. For critical business data to be viably handled on a network, the underlying platform must be robust enough to handle network-wide administration and management. It must also provide ample security to protect sensitive corporate information.

NetWare 4.0 allows better management control, easier maintenance, and more flexible security options than any other network operating system currently available. It is the ideal platform for today's sophisticated networking needs, and it will continue to support those needs as network computing evolves in the future.

This Application Note introduces some of the major new features of NetWare 4.0. For those familiar with previous versions of NetWare, it contains a feature-by-feature comparison of NetWare 4.0 and NetWare 3.11. More detailed information is contained in subsequent AppNotes in this issue.

NetWare 4.0 New Features

NetWare 4.0 inherits all the capabilities of earlier versions of NetWare and adds many new, exciting features. The most significant new features are the replacement of the bindery with NetWare Directory Services, increased security capabilities, and more flexible DOS client software. (These features, as well as installation, migration, and coexistence, are discussed in more detail in the other AppNotes in this issue.)

The sections which follow provide an overview of new features. For more information, refer to the NetWare 4.0 documentation.

NetWare Directory Services

In NetWare 4.0, the bindery has been replaced by NetWare Directory Services (NDS). NDS maintains a global, distributed, replicated database of information about network resources such as users, groups, servers, volumes, printers, computers, modems, and so on. With NDS, it is now possible to integrate a diverse network of resources into a single, easy-to-use environment.

The advantages of NDS are many. NDS provides a new network-wide login which makes network navigation and resource access easier for authorized users. Instead of logging in to specific servers, users can now login to the <u>network</u>. They can then access all the resources and services they have rights to, without having to explicitly login or attach to other servers. NDS handles all of the address resolution issues in the background, so users are shielded from the complexity of having to understand the network topology, protocols, media, and communication links.

Because the NDS database is replicated, multiple copies of users' required login information are spread throughout the network. This replication allows users to login to the network whether or not their home server is on-line. As long as the servers that provide the necessary data or services are operational, the user can access them. In this sense, when a user is logged in to the network, servers become transparent to the process of actually using the network. Users only need one password to gain access to all network resources available to them.

When a user accesses resources on the network (such as servers, volumes, and printers), authentication occurs in the background to verify that the user has rights to use those resources. NDS authentication works in combination with new access control features to provide network security.

More detailed information on NDS is contained in the NetWare Directory Services AppNotes in this issue.

Server Memory Management

NetWare's server memory management capabilities have been redesigned in NetWare 4.0 to increase efficiency. The server can now manage memory in a way that provides a better overall utilization of server memory, and which also prevents server applications from running out of memory.

In NetWare 3.11, the operating system allocates memory in five or more memory pools that serve different purposes. When server applications run, the memory they need is allocated from these pools. But when some applications finish running, the memory management routines do not always make the memory available to other applications. This can cause memory problems for other applications, as memory from one pool cannot be reallocated to another memory pool.

NetWare 4.0 has only one memory allocation pool, and memory used by one application can be reallocated when that application is finished with it. This improved memory management cuts down on the number of necessary operations and helps the server run more efficiently.

Data Storage Management

Many of today's new applications and data structures require significantly more storage space than in the past. NetWare 4.0 offers a number of new features that can help you manage increasing demands for data storage space.

Block Suballocation. Block suballocation allows small files, or that part of a file which exceeds the volume's default block size, to share a disk block with other files. This feature lets more files be stored in a smaller amount of space on a NetWare volume.

For example, in NetWare 3.11, if the default block size for a volume is 64 KB, and you create a 65 KB file, that file would use two complete disk blocks, or 128 KB. The remaining 63 KB in the second block is unused.

With NetWare 4.0's block suballocation feature enabled, any partially used disk block is divided into 512-byte suballocation blocks. These suballocation blocks are used to share the remainder of the block with any leftover fragments of other files. Using block suballocation in the example above, the system would allocate one disk block (64 KB) and two 512-byte suballocation blocks to store the 65 KB file. The remaining 63 KB of the second block is available for use by other files.

Block suballocation is enabled by default when NetWare 4.0 is installed.

File Compression. NetWare 4.0 provides a file compression feature which allows files to be compressed as they are saved to the hard disk. The files are automatically decompressed when they are retrieved. Enabling file compression lets NetWare volumes hold more on-line data by compressing files that are seldom accessed.

With this compression feature, you can effectively increase the amount of available disk space without adding new drives. The compression algorithm used can increase usable disk space up to 63%. For example, 600 MB of files on a volume could be compressed to as little as 222 MB. This can be a money-saving feature for environments where adding disk storage is financially prohibitive.

NetWare manages the file compression internally. Users (or the Supervisor) can flag individual files or directories either to be compressed after not being accessed for a time, or to never be compressed. When compression is enabled for a volume, the files flagged for compression are compressed after not being

accessed for the specified amount of time. Files are automatically decompressed when accessed by a user.

Data Migration. Another new feature of NetWare 4.0 is data migration. This feature enables servers to transfer data that is used infrequently to an off-line storage device such as a disk, CD-ROM, or tape drive. NetWare 4.0 still sees the data as residing on the NetWare volume. If the user requests a file stored off-line, the file will demigrate back to the server's hard disk.

Data migration frees up valuable hard disk space for frequently accessed files, while still allowing full access to the migrated files.

High Capacity Storage System. The High-Capacity Storage System (HCSS) is a data storage and retrieval system that extends the storage capacity of the NetWare server by integrating one or more optical library units, known as jukeboxes, into the NetWare file system. (A jukebox is a high-capacity storage device that uses an autochanger to mount and dismount optical disks automatically.)

The HCSS works with data migration to move files between faster, low-capacity storage devices (the server's hard disk) and slower, high-capacity storage devices (optical disks in a jukebox). It uses rewritable optical disks (either one-sided or two-sided) so that it is possible to repeatedly write and erase data.

The files and directories on the jukeboxes are accessed using the same NetWare commands and function calls used to access data from the hard disks. Access can be made by either users or programs.

HCSS uses free space on the server's hard disk to temporarily store (or cache) the most active files. When space is needed to store additional files and the allocated space reaches a predetermined capacity, the least-active files are transparently moved to optical disks.

When a user requests a file stored on optical disk, HCSS automatically copies the file from the jukebox back onto the server's hard disk. This process, known as demigration, allows users to access their most active files quickly.

Auditing

NetWare 4.0's auditing capabilities are much more powerful than in any previous versions of NetWare. Auditing allows authorized users (auditors) to audit past and present transactions on the network. These auditors act independently of network administrators to ensure that network records are accurate and confidential information is secure.

Transactions and events that can be monitored through NetWare 4.0 auditing include:

- Logins and logouts
- Trustee modifications
- File creations, deletions, reads, and writes
- Requests to manipulate queues
- Directory Services object creations, deletions, reads, and writes
- Events directly related to Directory Services objects
- Events directly related to users

With NetWare 4.0, auditors are able to track Directory Services events as well as file system and volume transactions. Auditing is enabled at the volume level for file system auditing, and at the container object level for Directory Services events.

Auditors should not be Supervisors and should not have SUPERVISOR rights or equivalence. Auditors can track events and activities on the network, but should not be able to open or modify network files (other than the Audit Data and Audit History files), unless they are granted rights to do so by the network supervisor.

The AUDITCON audit program files are automatically installed on your system when you install or upgrade to NetWare 4.0.

Other New Features

Running NLMs in Protected Mode. NetWare 4.0 has server memory protection features that guard OS memory from corruption by third-party NLMs. These features ensure that your server will not be halted by a faulty NLM.

Memory protection allows you to run NLMs in a separate memory domain called the OS_PROTECTED domain. After you have loaded an NLM in the OS_PROTECTED domain (ring 1, 2, or 3) and found it safe, you can load it into the OS domain (ring 0), where it can run most efficiently.

Note: All NLMs included with NetWare 4.0 have been tested and do not need to be run in an OS_PROTECTED domain.

Packet Burst Protocol. The packet burst protocol (or burst mode) capability which required a separate DOS client shell in NetWare 3.11 has been incorporated into the new client software. Packet burst is designed to transmit multipacket messages efficiently over an internetwork, which can result in faster data transmission between workstations and servers. Packet burst is enabled by loading PBURST.NLM on the server and entering a line in the workstation's NET.CFG file.

Large Internet Packets. The Large Internet Packet (LIP) feature allows increased throughput over network bridges or routers by increasing packet size. This feature is particularly helpful when using Ethernet or Token Ring architectures that allow larger packets to be sent over the network.

Multiple Languages. NetWare 4.0 has been adapted for use with multiple languages. The operating system, NLMs, and utilities use English as the default language, but they can be set to other languages as well. You can also set the server console keyboard for different languages.

NetWare Print Services. With NetWare 4.0, the hassle of having to know about print queues or print servers is eliminated. In bindery-based NetWare, only the print server and print queues exist as bindery objects; printers are defined as attributes of the print server. With NetWare Directory Services, print servers, print queues, and printers are all individual objects. They can be created and modified in any order with NetWare's text or graphical printing utilities.

One print server can now service up to 256 printers. Network printers can be attached directly to the network, to any NetWare server (via NPRINTER.NLM), or to DOS or OS/2 workstations (via NPRINTER.EXE). Users no longer need to know about print servers or print queues; they can send print jobs directly to a printer by specifying the printer name.

Other printing-related enhancements include support for:

- Configuring print queue polling time
- Unlimited number of print job configurations
- Third-party print job configurations
- Print jobs from Macintosh and NFS clients

NetWare 4.0 Utilities

The NetWare 4.0 utilities support Windows and OS/2 environments in addition to the DOS environment. Many utilities from earlier versions of NetWare have been consolidated into one, modified, or eliminated altogether. Also, new utilities and NLMs have been created for NetWare 4.0.

Figure 1 lists the NetWare 4.0 utilities, NLMs, and tools grouped according to functional categories. The Type column indicates the type of utility as follows:

Server Util Utilities which are entered at the server console prompt to monitor and control the network

Server NLM NetWare Loadable Modules which are loaded and run at the server

Text Util Character-based utilities which are run on DOS and OS/2 workstations

GUI Util New graphical user interface (GUI) utilities that allow supervisors to manage the network from Windows or OS/2 workstations

GUI Tools New graphical user interface (GUI) workstation tools that enable users to perform a variety of basic network tasks

Figure 1: NetWare 4.0 utilities grouped according to purpose.

```
NetWare Administrator GUI Util . Allows you to create
General
                                 ' NDS objects and assign
Administration (NWAdmin)
                                property values and rights. (Graphical
                                 counterpart of the
          NETADMIN text utility.)
          <sup>3</sup> NETADMIN
                         *Text Util * Menu-driven utility
                                 that allows you to
                                 create NDS objects and
                                 assign property values
                                 and rights.
                                 Consolidates SYSCON.
                                 DSPACE, SECURITY, and
                                 USERDE
          *Text Util * Allows you to create
          3 UIMPORT
                                 many User objects at
                                 the same time using a
                                 (non-NDS) database.
                                 Replaces MAKEUSER.
'Server NLM ' Lets you change SET
*Server
           *SFRVMAN
'Management
                                  * parameters in the .NCF
                                <sup>3</sup> files, and IPX/SPX,
                                device, volume, and network information.
                    'Server NLM ' Consolidates MONITOR ' and FCONSOLE.
          MONITOR.
                    *RCONSOLE
                          *Server NLM * Consolidates RCONSOLE
                                 and ACONSOLE.
                    <sup>3</sup> DOMAIN
                         *Server NLM * Creates a protected
                                 OS (OSP) domain to
                                 be run in Ring 1, 2,
                                 or 3. All new
                                * third-party NLMs
                                 should be developed
                                 and tested in an OSP
                                 domain.
                    3 NWSNUT
                          'Server NLM ' NLM Utility User
                                ¹ Interface module -
                                ¹ provides a library
```

```
* of routines used
                                 by certain NLMs
                                 ' (such as SERVMAN
                                  and MONITOR).
<sup>3</sup>NDS
                         GUI Util
           *Partition
                                <sup>3</sup> Allows you to manage
                                  * NDS partitions and
<sup>3</sup>Management
            *Administrator
                                 * replicas. (Part of
                                 * the NetWare
                                 Administrator
                     utility.)
           PARTMGR
                          *Text Util * Allows you to manage
                                 NDS partitions and
                                 ¹ replicas.
                     *TIMESYNC
                          *Server NLM * Controls time
                                  synchronization on
                     servers running NDS.
           <sup>3</sup>DSREPAIR
                          *Server NLM * Repairs and corrects
                                  problems in the NDS
                                  database (Similar
                                 ¹ to what BINDFIX
                                 and BINDREST did
for the bindery.)
*Storage
           *LIST DEVICES
                          'Server Util' Displays disk device
¹Management
                                  ¹ information for the
                                 <sup>1</sup> server.
                     'SCAN FOR NEW DEVICES 'Server Util' Scans for disk hardware '
                                 * that has been added
                                 ' since the server was
                                 ¹ last booted.
                     3 MAGAZINE
                          'Server Util' Confirms whether
                                 requests to insert
                                 ¹ and remove magazines
                                 ' in the server have
                                 ' or have not been
                                 * satisfied
                      3 MEDIA
                         'Server Util' Confirms whether
                                 <sup>3</sup> requests to insert
                                 and remove media in
                                 ¹ the server have or
                                 ¹ have not been
                                 * satisfied
                     ° CDROM
                          *Server NLM * Allows the server to
                                 ¹ use a CD-ROM disk as
                     <sup>a</sup>RTDM
                          'Server NLM ' Real Time Data
                                 Migration. (See)
                                 third-party
                                 * documentation.
*MIRROR STATUS
                          *Server Util* Displays all mirrored
Mirroring
                     ' logical disk portitions ' and their status.
                          <sup>3</sup>Server Util<sup>3</sup> Starts the remirroring
           *REMIRROR PARTITION
                                 of logical disk
                     *Server Util* Stops the remirroring
           *ABORT REMIRROR
                                 of logical disk
, portitions.
                        *Text Util * Consolidates FILER, * VOLINFO, SALVAGE,
*File
          'FILER
*Management
                                 and PURGE.
```

```
* FLAG *Text Util * Consolidates FLAG, * FLAGDIR, and SMODE. *
           *FLAG
                          *Text Util ' Consolidates RIGHTS, ' ALLOW, GRANT, REMOVE, '
3 Security
           *RIGHTS
and Auditing
                                  REVOKE, and TLIST.
                      *AUDITCON
                           Text Util ' Allows independent' auditors to audit
                                   network transactions,
                                  ' NDS events, and events
                                  * specific to a volume
                                   or server.
                                  1 (Consolidates ATOTAL
Print Server, Print
                                  <sup>a</sup> Queue, and Printer
                                  objects to set up
                                  ¹ the printing
                                  * environment
                      *NPRINTER
                          'Text Util ' Allows any printer
'Server NLM' to be used as a network'
' printer, whether
                                  attached to a DOS
or OS/2 workstation

    requests directed

                                  ' to it from the
network (Consolidates NBACKUP.)
*International- *KEYB
                          'Server Util' Allows you to select
                                  ³ a nationality or
¹ization
                      "Server Util" Sets the server or NLMs "
" to use a specific "
           *LANGUAGE
language.
                           'Server NLM ' Remote Program Load
Remote Boot
            'RPL
                                   enables remote
                                  booting of IBM
                                  * PC-compatible
                                  * diskless
'Text Util ' Consolidates ATTACH and '
<sup>3</sup>Client
          <sup>3</sup>LOGIN
'Utilities
                      <sup>a</sup>Text Util <sup>a</sup> Allows you to create
a menued working
           3 MENU
                      * environment for users. *
                           "Text Util " Allows users to access "
" network attachments, "
           NETUSER
                                  ' manage drive mappings,
                                  ¹ send messages, and set
                                  up print jobs.
(Replaces SESSION.)
                      3 NDIR
                          *Text Util * Consolidates NDIR,
                                  ' CHKDIR, LISTDIR, and
                       'NLIST
                          *Text Util * Allows users to view
                                  ' information about files,'
                                   directories, users,
                                   groups, volumes,
                                   servers, and queues.
                                  ¹ (Consolidates SLIST
```

NetWare Feature Comparison

Figure 2 provides a comparison of features common to NetWare 4.0 and NetWare 3.11, as well a listing of many features new with NetWare 4.0.

Figure 2: Feature comparison between NetWare 4.0 and 3.11.

```
*FFATURF
               NetWare 4.0 NetWare 3.11
*OPERATING SYSTEM ARCHITECTURE
Maximum number of user connections per '1000
                     ³250
*5, 10, 20, 50, *5, 10, 20, 50, *100, 250, 500, *100, 250
*User configuration (stratification)
              3 1000
*Maximum number of server connections per *50
                     38
              '(configurable '
'in client VLM) '
*client workstation
¹Yes (NetWare
                    ³No
*Object—based global naming service
               Directory
              *Services)
¹Yes
                    °No
MEMORY AND DISK REQUIREMENTS
FILE SYSTEM AND STORAGE
³Yes
                     ³No
Read-ahead cache
'Yes
                    ³No
Intelligent data compression
Support for data migration hardware
               *Yes
                    ¹No
'(optical jukebox, read/write optical,
³No
*Real—time Data Migration — High Capacity *Yes
*Storage System (HCSS)
*NETWORK SECURITY
*Restrict login to specific Medium Access *Yes (optional) *No
*Control addresses
```

| *Compression directory and file attribute | ³Yes | * No * No | , XXXXXXXXX |
|---|---|---|--|
| | Yes ¹ | No AAAAAAAAAAAAAAAA | 3 |
| *SECURITY AUDITING AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | | WAXAXAXXX ′ |
| | | *No 4AAAAAAAAAAA | AAAAAAAA ′ |
| | | *No 4AAAAAAAAAAAA | WAXAAAA ′ |
| Independent network auditor | | | AAAAAAAA ′ |
| 'Independent auditor password AXXAAXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX | 'Yes WWWWWW Yes | 'No XXXXXXXXXXXX 'No | WWW. |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | | XXXXXXXXX |
| ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ | AAAAAAAAAAAAAA | | ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| | | ************************************** | ÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | WWW.WW. | | * |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | res * | No | 3 |
| ÄAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | ³Yes | *No | 3 |
| *Transaction logs | *Yes | 4AAAAAAAAAAA 3 No | 3 |
| | 'Yes | ^a No | 1 |
| *Transaction monitoring/automatic log | AAAAAAAAAAAAAA ,'Yes | No. | ************ |
| 'updates AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX | | AAAAAAAA ′ |
| *NETWORK MANAGEMENT | | | 3 |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAA 'Yes | *No | AAAAAAAA ′ |
| ³privileges AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | , ,AAAAAAAAAAAAAA | 1 | , AAAAAAAAA |
| *View console operation status AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 'Yes WAAAAAAAAAAAAA | *No AAAAAAAAAAAA | ÄÄÄÄÄÄÄÄÄÄ |
| ³View supervisor equivalent status ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ | | | AAAAAAAA ′ |
| \$ | WAAAAAAAAAAAA | | , XXXXXXXX |
| | | *No *AAAAAAAAAAAA | WAXAAAAA ′ |
| Remote console modem callback AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | *Yes \AAAAAAAAAAAAAA \ | * No *********************************** | WAXAAAA |
| *NETWORK NAME SERVICES (Directory Servi AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | ces) AAAAAAAAAAAAAA 15 | ************************************** | WAXAAAA ′ |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 74es | | XXXXXXXXXXXXX |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | | XXXXXXXXX ′ |
| 'alias, organization, print server, queue, ' 'printer group, computer, directory map, | 3 | 3 | 3 |
| bindery objects, and so on) | | , 4AAAAAAAAAAAAAA | a AAAAAAAA ′ |
| ^a Extensible schema (set of objects and attributes) | 'Yes '(programmed) | 3 No | 3 |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | t *Unlimited | ³ N/A | WAXAAAAA ′ |
| 1 | "(default set of "attributes per | | 3 |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | object type) AAAAAAAAAAAAAA Unlimited | ************************************** | , XXXXXXXX |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | | , , , , , , |
| Partition database | *Yes *(logical *subtree) | *No | a a |
| | 'subtree) AAAAAAAAAAAAAAA | 4444444444444 | AAAAAAAA ′ |

| *Physical location of partitions | *One or more | 3N/A |
|---|--|---|
| , ÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃ | 'servers | , |
| *User—definable partitions XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX | 'Yes \\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\ | *N/A *********************************** |
| Partitions replicated across multiple servers | 'Yes | 'N/A |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 4AAAAAAAAAAAAA *Yes | ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 444444444444444444444444444444444444444 | AAAAAAAAAAAAAAAAAAAAAAAA |
| *Read—only partitions AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | |
| ¹Read/Write partitions ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ | | |
| *Background authentication AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | *N/A |
| *Background synchronization AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | *Yes \AAAAAAAAAAAAAAAA | * N/A * AAAAAAAAAAAAAAAAAAAAAAA |
| Protocol independent | ¹Yes \AAAAAAAAAAAAAAAA | *N/A AAAAAAAAAAAAAAAAAA |
| ³ Unicode enabled | ³Yes | 3 N/A |
| *External name service synchronization | ¹Yes | *N/A |
| *Object and property access rights (add, | ¹Yes | *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *delete, rename, move, read, compare, l *modify, browse) | ist," | 3 3 |
| ÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃ | AAAAAAAAAAAAA 'Yes | `AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | , No |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | |
| | | |
| *TIME SYNCHRONIZATION ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ | 4AAAAAAAAAAAAAA | * ************************************ |
| *International time zone support AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | ¹Yes \AAAAAAAAAAAAA | No AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| Daylight Savings Time support | ³Yes | 3 No 3 |
| *User-configurable time synchronization | *Yes | *No |
| *Single reference time server | *Yes (optional | *No * |
| 3 | *use of extern *atomic clock) | 1 |
| ÄAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 'Yes | ³No |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | ۹۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸۸ | `````````````````````````````````````` |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 4AAAAAAAAAAAAAAA °Yes (DOS, O | XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX |
| ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ | 165 (DOS, O. | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| | | *************************************** |
| Maximum shared printers per print serv | | |
| *RAM used on workstation—attached netw *printer | rork *4,976 byte *(parallel) | es '4-20 KB ' |
| 3 | °5,488 bytes °(serial) | 3 3 |
| ÃAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | *************************************** |
| ANETHODIC LITERIES | | 1 |
| *NETWORK UTILITIES AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | AAAAAAAAAAAAAAAAAAAAAAA |
| *Approximate number of utilities | *50 *(consolidated | '130 ' |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | | , XAXAXAXAXAXAXAXAXAXAXAXAXAX |
| AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| \(AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | `Yes | 74444444444444444444444444444444444444 |
| *Image manipulation AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | 444444444444444444444444444444444444444 | AAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Distributed data migration (Mass *Storage System — MSS) | *Yes | * No * |
| | | |

| AMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAM |
|---|
| *CLIENT SUPPORT AND INTEROPERABILITY *********************************** |
| **Supported Platforms **AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |

| ÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃ | ~ ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
|--|---|
| *File system (move, copy, trustees, | DOS, Windows, DOS |
| *salvage, rights) | ¹ PM ¹ |
| 20140de, Hights) | XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX |
| | |
| Directory services (create/delete | ^a DOS, Windows, ^a N/A |
| | ¹ PM |
| | *************************************** |
| *Search NDS Directory | ¹DOS, Windows, ¹N/A ³ |
| 3 | PM , |
| | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Move objects in Directory Services tree | DOS, Windows N/A |
| ÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃÃ | ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| Directory Services security | ³ DOS, Windows, ³ N/A |
| • | PM , |
| Αλλαλαλαλαλαλαλαλαλαλαλαλαλαλαλαλαλαλαλ | ``AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Directory Services partition management | |
| | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| Printing (queues, printers, print servers) | |
| ************************************** | ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| | ~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~ |
| * End User Tools | ~ ~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~ |
| | |
| *Change/Set Directory Services context | 'DOS, Windows, 'N/A |
| *************************************** | PM , |
| | XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX |
| Browse Directory Services | 'DOS, Windows, 'N/A ' |
| 3 | *PM |
| ÂAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| *User tools work with both bindery and | °DOS, Windows, °N/A |
| *Directory Services | 3 PM 3 3 |
| <u> </u> | ~ ÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄÄ |
| *Change file rights and attributes | DOS, Windows, DOS |
| 1 | *PM * |
| ΑλΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑΧΑ | ` AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| ³ Login | 'DOS, Windows, 'DOS ' |
| Login | |
| 1 | 3 DM 3 3 |
| 3 ************************************ | *PM |
| | |
| ³ Client install | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| ³ Client install | |
| ³ Client install | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install AXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install AXAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install **COLOR INTERFACE CARD SUPPORT ANAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMAMA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install **COLOR INTERFACE CARD SUPPORT **AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client account from type AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client account from type AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT **AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *Client install *NETWORK INTERFACE CARD SUPPORT *AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT **MANAMANAMANAMANAMANAMANAMANAMANAMANAMA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |
| *NETWORK INTERFACE CARD SUPPORT **MANAMANAMANAMANAMANAMANAMANAMANAMANAMA | AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA |