

DIMG

User Manual

Document Number: A000-UM01

January 2010

This document provides configuration and usage guidelines for the portable graphical edition of DIMG.

Revision/Update Information:	This is a new manual.
Operating System:	Microsoft Windows NT 5.0+; Linux
Software Version:	DIMG Version 1.0

Contents

1	Getting Started	1
1.1	Installation	1
1.1.1	Windows	1
1.1.2	Linux	1
1.2	Initial Configuration	2
1.2.1	Adding Drives on Linux	2
1.3	Working with Disk Image Files	3
2	Imaging Disks	7
2.1	Selecting a Drive	7
2.2	Reading	7
2.3	Writing	8
3	File Management	11
3.1	Browsing	11
3.2	Extracting Files	12
3.3	Viewing File Details	12
4	Advanced Topics	15
4.1	Plugin Architecture	15
4.1.1	Drive Access Plugins	15
4.1.2	Filesystem plugins	16
4.2	Plugin Loading	16
4.2.1	Filesystem Plugins	16
4.2.2	Drive Access Plugins	16
A	Troubleshooting	19
A.1	Missing Drives	19

List of Figures

1.1	The DIMG Main Window under Windows 7	2
1.2	Configure Driver in the Disk Menu	3
1.3	DQDLibDsk Driver configuration screen with no drives configured	3
1.4	DQDLibDsk Driver Prompt for Floppy Disk File	4
1.5	DQDLibDsk Driver configuration screen with drive added	4
1.6	DIMG Main Window showing a DOS 6.22 disk image loaded	5
2.1	Select Drive Menu	7
2.2	Reading Disk into Image File	8
2.3	Imaging Complete Message	8
2.4	Writing a disk	9
3.1	The contents of a DOS-6.22 disk image	11
3.2	File Properties	13

Chapter 1

Getting Started

DIMG is a utility for imaging floppy disks. It allows you to create a file which represents the exact content of the source disk which can then be restored onto another disk creating an exact copy.

In addition to basic reading and writing of disk images, DIMG provides the ability to view the contents of disk images as if they were archives. This allows files to be extracted from a disk image without having to write them to disk first.

Figure 1.1 shows DIMG's main window. In the center of the main window is the file view area. This shows files present in the currently open disk image. Figure 1.6 shows the DIMG main window again with an MS-DOS 6.22 boot disk image loaded.

1.1 Installation

1.1.1 Windows

On Windows, DIMG has no specific installation requirements. It will automatically initialise all settings required to default values on first run.

DIMG is made of these three components on Windows:

1. DIMG
2. DQWinDrv
3. fat12fs

1.1.2 Linux

DIMG is made of three components:

1. DIMG
2. DQDLibDsk
3. fat12fs




Figure 1.1: The DIMG Main Window under Windows 7

All three components require Qt 4.5 or higher. Additionally, DQDLibDsk requires that LibDsk be installed on the system.

To install DIMG on linux simply compile each of the three components (cd into the source directory and run `qmake` then `make`). This will produce a set of binaries (`dimg`, `libDQDLibdskdrv.so` and `libfat12fs.so`) which you can install to `/opt/dimg` by running `make install`.

1.2 Initial Configuration

1.2.1 Adding Drives on Linux

Some initial setup is required on Linux systems as DIMG is not able to automatically detect the systems floppy drives when using the DQDLibDsk driver (the default). To do this, select “Configure Driver” from the Disk menu (Figure 1.2) in the Main Window.

This will bring up the DQDLibDsk configuration screen (Figure 1.3 where you can manually add all floppy drives you wish to use on the system. To do this, Click on the Add button which will bring up a “Floppy Drive




Figure 1.2: Configure Driver in the Disk Menu

file” (Figure 1.4. This is where you can enter the name of the floppy drive (eg, `/dev/fd0`) or a raw image file which will be used as a virtual floppy drive. When you click OK the specified drive will be added to the list of floppy drives in the configuration screen (Figure 1.5).




Figure 1.3: DQDLibDsk Driver configuration screen with no drives configured

When the program is next started the specified floppy drive(s) will appear in the Drive Select menu.

1.3 Working with Disk Image Files

To open a disk image you can either pass the filename you wish to open to `DIMG` on the commandline (for example, `./dimg /tmp/file.img`) or select Open from the File menu.

Selecting Open from the File menu will display a standard file open dialog which you can use to locate a supported disk image file. Only raw disk image files formatted with the FAT-12 filesystem are currently supported. Trying to open disk images with other filesystems or corrupt filesystems may require the FAT-12 filesystem plugin to be disabled to prevent malfunction.




Figure 1.4: DQDLibDsk Driver Prompt for Floppy Disk File




Figure 1.5: DQDLibDsk Driver configuration screen with drive added

Support for disk images generally follows support for disk types - as DMF disks are unsupported trying to open a DMF-format raw disk image will cause bad things to happen (program crashes).

Once a supported disk image has been opened its contents will be displayed in the main window such as in Figure 1.6. The name of the file loaded is shown in the title bar and the images volume label is shown in the status bar at the bottom of the main window. In this case, the volume label is D0S622B00T.

To write an image to a disk see Section 2.3.

The image can be closed again by choosing *Close Image* from the File Menu. This will close the disk image and return the program to how it looked before the image was open (Figure 1.1).




Figure 1.6: DIMG Main Window showing a DOS 6.22 disk image loaded

Chapter 2

Imaging Disks

The primary function of DIMG is to image disks. This includes both reading a disk to image and writing an image to a disk. At this stage DIMG only supports working with Floppy Disk images. This version has only been tested with 3.5" high density disks but will probably work with other varieties. In particular, DMF formatted disks are not currently supported.

2.1 Selecting a Drive

Before you can image a disk you must select the drive containing the disk you wish to image. To do this select the desired drive from the Select Drive submenu of the Disk menu (See Figure 2.1).




Figure 2.1: Select Drive Menu

If the Select Drive menu is empty or the desired drive is missing, see Section A.1 (Troubleshooting Missing Drives)

The drive you select will remain selected until either you select a different drive or restart the program. All image read or write operations will be performed on this drive for as long as it is selected.

2.2 Reading

Before a disk can be read into an image file the drive containing the disk you wish to image must be selected (See Section 2.1).

To read a disk into an image file, choose *Read Disk* from the *Disk* menu (See Figure 2.1). If a disk is present in the selected drive DIMG should start reading

the image immediately provided your user account has access to the selected drive.

When DIMG is reading a disk into an image file it will show a progress dialog like the one shown in Figure 2.2. Clicking the Cancel button will cancel the read process.




Figure 2.2: Reading Disk into Image File

When imaging has completed a message will appear (Figure 2.3) and the filesystem on the disk will be displayed.




Figure 2.3: Imaging Complete Message

An image of the disk now resides in memory. If you wish to keep the disk image you have just created you must then save it by choosing *Save* from the *File* menu.

2.3 Writing

The basic process for writing a disk image to disk much the same as reading a disk into memory and then saving it to a file - just in reverse. Essentially, all you must do is:

1. Open the disk image you wish to write.
2. Choose the drive you wish to write it to.
3. Start the write process.
4. Wait for it to finish.

Before you can write a disk image to disk you need to have that disk image open. You can either load a disk image file into memory (See section 1.3) or you can read a disk directly into memory (Section 2.2).

Next you must select the drive you wish to write the disk image to (Section 2.1). Make sure you select the correct drive as any existing data on the disk in that drive will be erased. Once this is done you may start the actual disk imaging process.

Lastly, choose *Write Disk* from the Disk menu. A progress dialog (Image 2.4) will appear and, should no errors occur, a “Disk Imaging Complete.” message (Image 2.3) will eventually appear. The disk in the selected drive should now be an exact copy of the original source disk or disk image file.




Figure 2.4: Writing a disk

If errors have occurred, try replacing the disk you are writing to or clean the drive. Despite what error messages may say, this version of DIMG is not capable of retrying reads or writes. If a read or write fails you have to start again.

Chapter 3

File Management

This chapter explains how you can treat a disk image file like you would an archive/zip file. This includes browsing its contents and extracting files without having to write the image back to disk.

3.1 Browsing

When you open a disk image file or read in a disk with a **valid** and **non-corrupt** (important) FAT-12 filesystem on it (most PC disks use this filesystem) you will see all of the files and directories present on the disk in the main window (Image 3.1). To see the contents of a directory, click on the expand symbol next to the folder icon.




Figure 3.1: The contents of a DOS-6.22 disk image

Four columns are shown in the file area of the main window. These are Filename, Attributes, Size and Date Modified. The contents of all these except perhaps attributes should be fairly obvious.

The attributes column shows which attributes the file has set. These attributes are:

Attribute letter	Attribute Name
r	Read-Only
h	Hidden
a	Archive
r	System
d	Directory

3.2 Extracting Files

Like an archive, all of the files you see in the disk image can be extracted to a location on your computer without having to write the disk image out to a disk first. To extract a file, right click on the desired file and choose Extract File. A save dialog will appear where you can choose where to extract the file to and what to name it.

3.3 Viewing File Details

To view the full details of a file, right click on the desired file and choose the *File Properties* option. This will display a properties dialog similar to the one in Figure 3.2.




Figure 3.2: File Properties

Chapter 4

Advanced Topics

4.1 Plugin Architecture

DIMG has been designed with a modular architecture to allow various components to be upgraded or replaced without requiring major changes to other components.

At this time there are three main components:

1. DIMG - the main program
2. Filesystem plugin - Provides access to a disk images filesystem
3. Drive Access plugin - Provides access to the systems floppy drives.

At this stage only one of each component can be active at a time. That means that DIMG can only support a single filesystem at a time - if you replace the FAT12 filesystem plugin with an HFS one you will no longer be able to see the contents of FAT12 disks.

4.1.1 Drive Access Plugins

The Drive Access Plugin is responsible for providing access to the systems floppy drive. It handles all reading and writing of disks. Currently there are two available Drive Access Plugins:

DQDLibDsk

A portable drive access plugin which uses LibDsk to do most of the work. This plugin has some serious performance issues on Windows systems and so is only provided with Linux versions of DIMG.

DQWindrv

This Windows-only Drive Access Plugin is a lot simpler than DQDLibDsk but provides significantly better performance. It is the default Drive Access Plugin for Windows systems.

4.1.2 Filesystem plugins

Filesystem plugins provide access to the filesystem on a disk image allowing files to be extracted as if it were an archive. At this stage only one Filesystem plugin is provided - FAT12fs. This plugin provides access to the FAT12 filesystem commonly used on PC-formatted floppy disks.

4.2 Plugin Loading

On startup DIMG tries to load plugins using a number of default filenames trying each one until something loads. The filenames depend on the operating system in use and the type of build (debug or release). The format of filenames can be summarised in table 4.1.

Platform	Build Type	Prefix	Suffix	Extension
Windows	Debug		d	.dll
	Release			
UNIX	Debug	lib	d	.so
	Release			

Table 4.1: Plugin filename components

So the DQDLibdisk (DQlibdiskdrv) plugins filename on windows for a debug build would be `DQlibdiskdrvd.dll`. On linux for a release build it would be `libDQlibdiskdrv.so`.

4.2.1 Filesystem Plugins

For Filesystem plugins DIMG will first try to load the `fat12fs` plugin moving on to `fsplugin` should it not be found. Should neither plugin exist it will display a File Open dialog allowing you to browse for a Filesystem plugin.

Applying the rules in table 4.1 a windows release build would first try to load `fat12fs.dll` and then `fsplugin.dll`.

4.2.2 Drive Access Plugins

The loading of Drive Access Plugins is similar to that of Filesystem Plugins (see section 4.2.1) except for a few minor differences.

The first plugin filename DIMG tries depends on the platform. It tries to load `DQlibdiskdrv` on UNIX platforms or `DQWindrv` on Windows. On both platforms it will then attempt to load `dqplugin` before displaying a File Open dialog allowing you to browse for a Drive Access plugin.

Unlike with filesystem plugins, this process can be overridden by specifying the plugin name in the DIMG configuration file. On UNIX this can be done by adding the key `DQDriver = someplugin` under the `Plugins` group in the configuration file `~/config/zxnet/DIMG.conf`.

On windows, the key `HKEY_CURRENT_USER\Software\zxnet\DIMG\Plugins` should be created with the String value `DQDriver` set to the name of the plugin to load.

Should the specified plugin fail to load, DIMG will fall back to the default behaviour (trying the two default filenames before prompting).

Appendix A

Troubleshooting

A.1 Missing Drives

On Windows, DIMG attempts to automatically detect all supported drives on startup. If the desired drive is not visible it may be that it is not supported or was not connected when DIMG started.

On Linux DIMG is unable to automatically detect supported drives. Drives must be manually configured - see Section 1.2.1 for instructions on how to do this.

Problem	Possible Cause	Action
The Select Drive menu is empty	No supported drives are present (Windows)	Attach a supported drive and restart DIMG
	No drives are configured (Linux)	Configure drives on the system (Section 1.2.1)
One drive not available in Select Drive menu while others are	The drive may not be supported	Use a different drive type
	Drive was attached after DIMG was started (Windows)	Restart DIMG